
	<p>module description</p> <p>Project: <b>MSS54</b> Module: <b>Diagnosis probe heating</b></p>	<p>Page 1 of 8</p>
---	---	--------------------

## Project: MSS54


### Module: Diagnosis of lambda sensor heater

	Department	Date	name	Filename
editor	EE-32	16.04.2013		5.10

	<p style="text-align: center;">module description</p> <p>Project: <b>MSS54</b> Module: <b>Diagnosis probe heating</b></p>	<p>Page 2 of 8</p>
---	---	--------------------

<b>1. GENERAL</b>	<b>3</b>
<b>2. CONDITION FOR ACTIVATION OF THE DIAGNOSIS</b>	<b>3</b>
<b>3. HEATING PERFORMANCE DIAGNOSIS USING A RESISTANCE TEST</b>	<b>4</b>
3.1. Test criteria	4
3.2. Error checking	4
<b>4. DETERMINING THE HEATER RESISTANCE</b>	<b>5</b>
4.1. Current measurement via the driver module	5
4.2. Determining the resistance of the heater	6
<b>5. LSH DRIVER DIAGNOSIS</b>	<b>6</b>
<b>6. CONSTANTS AND VARIABLES</b>	<b>7</b>
6.1. Constants	7
6.2. Variables	8

	Department	Date	name	Filename
editor	EE-32	16.04.2013		5.10

	<b>module description</b> Project: <b>MSS54</b> Module: <b>Diagnosis probe heating</b>	Page 3 of 8
---	---	-------------

## 1st General

The lambda sensor heater is checked with two diagnostic functions:

- electrical diagnosis
- Diagnosis of heating performance

The electrical diagnosis is carried out via a driver diagnosis. The driver provides the information as to whether there is a short circuit to ground, to UBATT or whether there is an open circuit.

To diagnose the heating output, the heater current of the VKAT or VKAT-T is measured for each exhaust system. NKAT probe heating is used. The current can be measured via the driver used for the probe heating. The heater current is determined every 10ms, the diagnosis itself is carried out in the background task.

## 2nd activation condition for the diagnosis

Both diagnostic functions have common activation conditions.


Since the heater resistance is initially low when the probe is cold, no diagnosis is initiated at this point. The probe heater is initially heated to maximum until the probe is ready for operation. It is then heated at reduced heating power until the dew point is exceeded. To ensure that the heater current has fallen to its steady-state value, a certain amount of time is waited after the dew point has been exceeded before diagnosis is started.

### Conditions:

- all switch-on conditions for the lambda probe heating are met  
=> B\_LSHV1/2\_ON for the VKAT sensors  
B\_LSHN1/2\_ON for the NKAT probes
- the dew point for the individual probes is exceeded  
=> !B\_LSHV1/2\_TAUP for the VKAT probes  
!B\_LSHN1/2\_TAUP for the NKAT probes
- the dew point condition is fulfilled for the time K\_LSHV/N\_TAUP\_T  
(the time is only started when the heating is switched on)
- the battery voltage ubatt > K\_ED\_UBMIN is
- the LS heater is not controlled via DS2 (!B\_LSHxx\_DS2)
- Check whether it is a single-flow or double-flow exhaust system.  
(B\_CFG\_S50 || B\_CFG\_S62)

	Department	Date	name	Filename
editor	EE-32	16.04.2013		5.10

11:53:00

	<p style="text-align: center;"><b>module description</b></p> <p>Project: <b>MSS54</b> Module: <b>Diagnosis probe heating</b></p>	<p style="text-align: right;">Page 4 of 8</p>
---	--	---

### 3. Heating performance diagnosis based on a resistance test

#### 3.1. Test criteria

The heater resistance of the probes is used as a diagnostic criterion.

Different resistance thresholds are used for the VKAT and NKAT probes

VKAT: K_LSHV1/2_DIAG_RO	upper diagnostic threshold	(approx. 18.6 ohms)
	lower diagnostic threshold	(approx. 4.5 ohms)
NKAT: K_LSHN1/2_DIAG_RO	upper diagnostic threshold	(approx. 18.6 ohms)
	lower diagnostic threshold	(approx. 4.5 ohms)

#### 3.2. Error checking

##### **Error - Heating output too low:**

If the resistance test shows that the heater resistance

for the VKAT probe:

$\text{lshv\_diag\_r1 or lshv\_diag\_r2} > \text{K\_LSHV1/2\_DIAG\_RO}$

for the NKAT probe:

$\text{lshn\_diag\_r1 or lshn\_diag\_r2} > \text{K\_LSHN1/2\_DIAG\_RO}$

the heating output of the probe heater is too low and an error is detected.

##### **Error - heating output too high/ no heating output:**

If the resistance test shows that the heater resistance

for the VKAT probe:

$\text{lshv\_diag\_r1 or lshv\_diag\_r2} < \text{K\_LSHV1/2\_DIAG\_RU}$

for the NKAT probe:


$\text{lshn\_diag\_r1 or lshn\_diag\_r2} < \text{K\_LSHN1/2\_DIAG\_RU}$

The heating output of the probe heater is too high or there is no heating output; thus an error is detected.

With the help of the diagnostic function **ed\_report**, as soon as one of these errors is detected, the error type **"IMPLAUSIBLE"** is entered into the error memory.

	Department	Date	name	Filename
editor	EE-32	16.04.2013		5.10

11:53:00

	<b>module description</b> Project: <b>MSS54</b> Module: <b>Diagnosis probe heating</b>	Page 5 of 8
---	---	-------------

***no error - resistance value is within the thresholds:***

If the determined resistance of the heater is within the upper and lower thresholds, no error can be detected; ie the lambda probe heater is working properly. If an error of the type "IMPLAUSIBLE" is entered in the error log, the **ed\_report** function is called with the error type "No error" to correct it.

4th **Determination of the heater resistance**

### 4.1. Current measurement via the driver module

The *ATM38 driver* used for the lambda sensor heater is used to measure the heater current.

The driver voltage is detected on the slave at ports PQA4 - PQA7 (LHV1, LHV2, LHN1 and LHN2).

These voltage values are converted by the A/D converter into a 10-bit value (0V = 0; 5V = 1024) and stored in the variables AD\_KANAL\_LSHV1/2 and AD\_KANAL\_LSHN1/2.

However, care must be taken that the voltage is not exceeded during any LSH control 5V and decreases accordingly when activated. The signal is thus inverted, which is compensated for by software.

**Voltage conditioning:**

*According to the data sheet:*

$$i_{lsh} = u_{lsh} \cdot 650 / 681 \text{ Ohm}$$

$$u_{lsh} = 5V - \text{AD\_KANAL value}$$


*In the processor:*

$$lshx_{iy\_ad} = 1024 - \text{AD\_KANAL\_LSHxy}$$

Conversion to current value: HEX / 215 for the ad

	Department	Date	name	Filename
editor	EE-32	16.04.2013		5.10

11:53:00

	<b>module description</b>  Project: <b>MSS54</b> Module: <b>Diagnosis probe heating</b>	Page 6 of 8
---	---	-------------

## 4.2. Determining the resistance of the heater

Since the battery voltage is a known system quantity, the determined current to determine the actual heater resistance.

$$I_{shx\_diag\_ry} = u_b \cdot LSH\_OHM\_FAK / I_{shx\_iy}$$

$I_{shx\_diag\_ry}$ : Resistance of the heater of the VKAT- or NKAT probes

$I_{shx\_iy}$ : Heater current of the VKAT or NKAT probes

$u_b$ : measured battery voltage

$LSH\_OHM\_FAK$ : Conversion factor of the AD value to the current value (215dec)

This resistance determination is carried out every 10ms.

Since the probe heating is controlled by pulse width modulation with a period of 200msec, the current is averaged in order to obtain the actual resistance value. To do this, a measured value (AD value) is saved and summed up every 10ms over 2 periods. In this way, an average value can be calculated over 40 measured values. However, this averaged current is not yet the actual current value, since the averaging also takes place over LOW times of the PWM signal. The duty cycle used must therefore be included in the calculation.

*Current value determination:*

$$I_{shx\_iy} = I_{shx\_iy\_sum} \cdot (100 / LSH\_I\_SUM\_FAK) / I_{shxy\_ta}$$

$I_{shxy\_ta}$ : Duty cycle for LSH- VKAT or NKAT

$I_{shx\_iy\_sum}$ : accumulated current values 40

$LSH\_I\_SUM\_FAK$ : measured values

### 5th LSH driver diagnostics

The LSH driver **ATM38** also diagnoses the following electrical errors:

- openload = interruption
- Short circuit to UB
- Short circuit to ground


When evaluating the driver module, however, it must be ensured that the driver is read out at an angle-synchronous level.

To avoid "turbo effects", the driver diagnosis must not take place more than once within the LSH period (driver-specific).

Since the

	Department	Date	name	Filename
editor	EE-32	16.04.2013		5.10

11:53:00

	<b>module description</b> Project: <b>MSS54</b> Module: <b>Diagnosis probe heating</b>	Page 7 of 8
---	---	-------------

If the heating output diagnosis takes place every other period, this diagnosis is also carried out in this grid.

The driver diagnosis has priority over the heating performance diagnosis, which means that an error recorded by the electrical diagnosis gets through and the heating performance diagnosis is skipped.

With the help of the diagnostic function **ed\_report**, as soon as an error is detected, the corresponding error type is entered into the error memory.

If there is no electrical error and an error of the type "SH\_TO\_UB, SH\_TO\_GND or OPENLOAD" is entered in the error memory, the **ed\_report** function is called with the error type "No error" to correct it.

The following transfer parameters to the **ed\_report** are now possible in total:

0x00: no error (NO\_ERROR)  
 0x01: short to battery (SH\_TO\_UB)  
 0x02: short to ground (SH\_TO\_GND)  
 0x04: openload  
 0x08: implausible (heating power)

As soon as an error is entered in the error memory, the state B\_LSHV1/2\_ERROR for the VKAT or B\_LSHN1/2\_ERROR for the NKAT sensor is set.

#### A diagnostic error of the probe heater affects:

- the release of the NKAT controller (laaktiv.c)
- the probe diagnosis of the VKAT and NKAT (ladiag.c)
- Catalyst conversion (la\_obd.c)
- Lambda sensor aging monitoring (la\_obd.c)


## 6th constants and variables

### 6.1. Constants

<b>K_LSH_TAUP_T</b>	Time that must have elapsed after exceeding the dew point
<b>K_LSHV1_DIAG_RU</b>	lower resistance threshold for the diagnosis VKAT1
<b>K_LSHV2_DIAG_RU</b>	lower resistance threshold for the diagnosis VKAT2
<b>K_LSHN1_DIAG_RU</b>	lower resistance threshold for the diagnosis NKAT1
<b>K_LSHN2_DIAG_RU</b>	lower resistance threshold for the diagnosis NKAT2

	Department	Date	name	Filename
editor	EE-32	16.04.2013		5.10

11:53:00

	<b>module description</b> Project: <b>MSS54</b> Module: <b>Diagnosis probe heating</b>	Page 8 of 8
---	---	-------------

<b>K_LSHV1_DIAG_RO</b>	upper resistance threshold for the diagnosis VKAT1
<b>K_LSHV2_DIAG_RO</b>	upper resistance threshold for the diagnosis VKAT2
<b>K_LSHN1_DIAG_RO</b>	upper resistance threshold for the diagnosis NKAT1
<b>K_LSHN2_DIAG_RO</b>	upper resistance threshold for the diagnosis NKAT2

## 6.2. Variables

<b>Ishv_i1/2</b>	current value VKAT1/2
<b>Ishn_i1/2</b>	current value NKAT1/2
<b>Ishv_i1_ad</b>	"inverted" AD value VKAT2 (current)
<b>Ishn_i2_ad</b>	"inverted" AD value NKAT2 (current)
<b>Ishv_i1/2_counter</b>	counter to sum the current values VKAT1/2
<b>Ishn_i1/2_counter</b>	counter to sum the current values NKAT1/2
<b>Ishv_i1/2_sum</b>	summed AD values VKAT1/2
<b>Ishn_i1/2_sum</b>	summed AD values NKAT1/2
<b>Ishv_diag_r1</b>	actual resistance value VKAT1
<b>Ishv_diag_r2</b>	actual resistance value VKAT2
<b>Ishn_diag_r1</b>	actual resistance value NKAT1
<b>Ishn_diag_r2</b>	actual resistance value NKAT2
<b>Ishv1/2_ed</b>	Error status variable for VKAT1/2
<b>Ishn1/2_ed</b>	Error status variable for NKAT1/2
<b>Ishv1/2_tr_ed</b>	Driver status variable for VKAT1/2
<b>Ishn1/2_tr_ed</b>	Driver status variable for NKAT1/2

	Department	Date	name	Filename
editor	EE-32	16.04.2013		5.10